

Infrastructure Systems

- [How To: Change the IP Address of a Proxmox Clustered Node](#)
- [How To: Mount SMB Shares on a Pi](#)

How To: Change the IP Address of a Proxmox Clustered Node

If changing entire subnet:

(e.g. 192.168.1.0/24 to 192.168.2.0/24)

```
# Stop the cluster services
systemctl stop pve-cluster
systemctl stop corosync

# Mount the filesystem locally
pmxcfs -l

# Edit the network interfaces file to have the new IP information
# Be sure to replace both the address and gateway
vi /etc/network/interfaces

# Replace any host entries with the new IP addresses
vi /etc/hosts

# Change the DNS server as necessary
vi /etc/resolv.conf

# Edit the corosync file and replace the old IPs with the new IPs for all hosts
# :%s/192\.168\.1\. /192.168.2. /g <- vi command to replace all instances
# BE SURE TO INCREMENT THE config_version: x LINE BY ONE TO ENSURE THE CONFIG IS NOT
OVERWRITTEN
vi /etc/pve/corosync.conf

# Edit the known hosts file to have the correct IPs
```

```
# : %s/192\.168\.1\. /192.168.2. /g <- vi command to replace all instances
/etc/pve/priv/known_hosts

# If using ceph, edit the ceph configuration file to reflect the new network
# (thanks u/FortunatelyLethal)
# : %s/192\.168\.1\. /192.168.2. /g <- vi command to replace all instances
vi /etc/ceph/ceph.conf

# If you want to be granular... fix the IP in /etc/issue
vi /etc/issue

# Verify there aren't any stragglers with the old IP hanging around
cd /etc
grep -R '192\.168\.1\.' *
cd /var
grep -R '192\.168\.1\.' *

# Reboot the system to cleanly restart all the networking and services
reboot

# Referenced pages:
# - https://forum.proxmox.com/threads/change-cluster-nodes-ip-addresses.33406/
# - https://pve.proxmox.com/wiki/Cluster\_Manager#\_remove\_a\_cluster\_node
```

If changing only the IP:

(e.g. 192.168.1.10/24 to 192.168.1.20/24)

```
# Stop the cluster services
systemctl stop pve-cluster
systemctl stop corosync

# Mount the filesystem locally
pmxcfs -l

# Edit the network interfaces file to have the new IP information
vi /etc/network/interfaces

# Replace any host entries with the new IP addresses
```

```
vi /etc/hosts

# Edit the corosync file and replace the old IPs with the new IPs for any changed hosts
# BE SURE TO INCREMENT THE config_version: x LINE BY ONE TO ENSURE THE CONFIG IS NOT
OVERWRITTEN
vi /etc/pve/corosync.conf

# Edit the known hosts file to have the new IP(s)
/etc/pve/priv/known_hosts

# If using ceph, edit the ceph configuration file to reflect the new network
# (thanks u/FortunatelyLethal)
# :%s/192\.168\.1\. /192.168.2. /g <- vi command to replace all instances
vi /etc/ceph/ceph.conf

# If you want to be granular... fix the IP in /etc/issue
vi /etc/issue

# Verify there aren't any stragglers with the old IP hanging around
cd /etc
grep -R '192\.168\.1\.' *
cd /var
grep -R '192\.168\.1\.' *

# Reboot the system to cleanly restart all the networking and services
reboot

# Referenced pages:
# - https://forum.proxmox.com/threads/change-cluster-nodes-ip-addresses.33406/
# - https://pve.proxmox.com/wiki/Cluster\_Manager#\_remove\_a\_cluster\_node
```

How To: Mount SMB Shares on a Pi

<https://linuxize.com/post/how-to-mount-cifs-windows-share-on-linux/>

tl;dr (assuming user/share is set up on freenas)

1. Install cifs-utils and create your mount directory
2. Create a credentials file */etc/win-credentials-app*
3. Populate with *username=* and *password=* on two lines in plaintext (scary, I know)
4. Chown root: and chmod 600 to have a thin veil of security

5. One-off mount:

```
sudo mount -t cifs -o credentials=/etc/win-credentials-app,dirmode=0755,uid=1000,gid=1000 //freenas.lan/app /app
```

Replace win-credentials-app with your credentials file and 1000/1000 with your user's user/group IDs.

6. Auto-mount: (add to */etc/fstab*)

```
//freenas.lan/app /app cifs credentials=/etc/win-credentials-app,file_mode=0755,uid=1000,gid=1000 0 0
```

7. Will mount automatically on boot. Use *sudo mount /app* or *sudo umount /app* to manually mount/unmount with an fstab entry.